ADMIN CONSOLE > USER MANAGEMENT >

Microsoft Entra ID SCIM Integration

View in the help center: https://bitwarden.com/help/microsoft-entra-id-scim-integration/

Microsoft Entra ID SCIM Integration

System for cross-domain identity management (SCIM) can be used to automatically provision and de-provision members and groups in your Bitwarden organization.

() Note

SCIM Integrations are available for **Teams and Enterprise organizations**. Customers not using a SCIM-compatible identity provider may consider using Directory Connector as an alternative means of provisioning.

This article will help you configure a SCIM integration with Azure. Configuration involves working simultaneously with the Bitwarden web vault and Azure Portal. As you proceed, we recommend having both readily available and completing steps in the order they are documented.

∂ Tip

Already an expert? Skip the instructions in this article and download the quick configuration guide to setup SSO and SCIM with Entra ID.

↓ Quick reference guide

Enable SCIM

Note

Are you self-hosting Bitwarden? If so, complete these steps to enable SCIM for your server before proceeding.

To start your SCIM integration, open the Admin Console and navigate to Settings → SCIM provisioning:

D bit warden		SCIM provisioning	
	~ ~ ~	SCIM provision users and groups with your preferred identity provider via SCIM provisioning C Enable SCIM SCIM URL C CIM API key This API key has access to manage users within your organization. It should be kept secret. Sorre	
Single sign-on Device approvals SCIM provisioning			

SCIM provisioning

Select the

Create an enterprise application

∂ Tip

If you are already using this IdP for Login with SSO, open that existing enterprise application and skip to this step. Otherwise, proceed with this section to create a new application

In the Azure Portal, navigate to Microsoft Entra ID and select Enterprise applications from the navigation menu:

Home >

«	🕂 Add \vee 🐯 Manage tenants 🖪 What's new 🛛 🗟 Preview f	ieatures 🛛 🔗 Got feedback? 🗸	
j Overview	Overview Monitoring Properties Recommendations	Tutorials	
Preview features			
Diagnose and solve problems	Search your tenant		
lanage	Basic information		
Users			
Groups	Name	Users	
External Identities	Tenant ID	Groups	
Roles and administrators	Primary domain	Applications	
Administrative units	License Devices		
Delegated admin partners			
Enterprise applications	Alerts		
Devices			
App registrations	Microsoft Entra Connect v1 Retirement All version 1.x builds of Microsoft Entra Connect	Azure AD is now Microsoft Entra ID Microsoft Entra ID is the new name for Azure Active	
Identity Governance	(formerly AAD Connect) will soon stop working between October 2023 – March 2024. You must move		
Application proxy	to Cloud Sync or Microsoft Entra Connect v2.x.		
Custom security attributes	Learn more 🖸	Learn more 🖸	

Select the + **New application** button:

Home > Enterprise applications Enterprise applicati Default Directory - Microsoft Entra ID	ons All applications	×
« Overview	🕂 New application 🖰 Refresh 🞍 Download (Export) 🚯 Preview info 🇮 Columns 🖾 Preview features 🖗 Got feedback?	
Overview	View, filter, and search applications in your organization that are set up to use your Microsoft Entra tenant as their Identity Provider.	
X Diagnose and solve problems	The list of applications that are maintained by your organization are in application registrations.	
Manage		

Create new application

On the Browse Microsoft Entra ID Gallery screen, select the + Create your own application button:

Home > Default Directory | Enterprise applications > Enterprise applications > Enterprise applications > All application > All = Account Management : All application > All = Account Management : All = Categories : All

Create your own application

On the Create your own application screen, give the application a unique, Bitwarden-specific name. Choose the **Non-gallery** option and then select the **Create** button.

Х

Create your own application



D bitwarden

If you are developing your own application, using Application Proxy, or want to integrate an application that is not in the gallery, you can create your own application here.

What's the name of your app?

Input name


What are you looking to do with your application?

- Configure Application Proxy for secure remote access to an on-premises application
- Register an application to integrate with Microsoft Entra ID (App you're developing)
- Integrate any other application you don't find in the gallery (Non-gallery)

Create Entra ID app

Enable provisioning Select **Provisioning** from the navigation and complete the following steps:

×



Select Provisioning

1. Select the **Get started** button.

2. Select Automatic from the Provisioning Mode dropdown menu.

- 3. Enter your SCIM URL (learn more) in the Tenant URL field.
- 4. Enter your SCIM API Key (learn more) in the Secret Token field.
- 5. Select the Test Connection button.
- 6. If your connection test successfully, select the Save button.

Mappings

This screen is available while performing initial setup for the Enterprise Application, or by navigating to the Enterprise Application, and selecting **Provisioning** under the **Manage** section of the left-hand menu, and then selecting **Edit Provisioning** at the top.

Bitwarden uses standard SCIM v2 attribute names, though these may differ from Microsoft Entra ID attribute names. The default mappings will work, but you can use this section to make changes if you wish.

User mapping

If you would like User objects in your directory to synchronize with Bitwarden, you may enable or disable **Provision Microsoft Entra ID Users**. This is enabled by default. Select the **Provision Microsoft Entra ID Users** link to customize the attributes sent to Bitwarden with the user objects if you wish to make changes according to the following table:

Bitwarden attribute	Default AAD attribute
active	<pre>Switch([IsSoftDeleted], , "False", "True", "True", "False")</pre>

Bitwarden attribute	Default AAD attribute
emails ^a or userName	mail or user Principal Name
displayName	displayName
externalId	mailNickname

^a - Because SCIM allows users to have multiple email addresses expressed as an array of objects, Bitwarden will use the value of the object which contains "primary": true.

Group mapping

If you would like Group objects in your directory to synchronize with Bitwarden, you may enable or disable **Provision Microsoft Entra ID Groups**. This option is enabled by default. Select the **Provision Microsoft Entra ID Groups** link to customize the attributes sent to Bitwarden with the groups objects if you wish to make changes according to the following table:

Bitwarden attribute	Default AAD attribute
displayName	displayName
members	members
externalId	objectId


Settings

Under the **Settings** dropdown, choose:

- Whether to send an email notification when failure occurs, and if so, what address to send it to (recommended).
- Whether to **sync only assigned users and groups** or **sync all users and groups**. This setting is modified based your Mapping configuration. For example, if Group mapping is disabled, Groups added to the Enterprise Application will synchronize only the User objects who are members of the Group, and not create the Group in Bitwarden itself. If you choose to sync all users and groups, skip the next step, as your entire directory will be synchronized, depending on your Mapping settings.

Assign users and groups

Complete this step if you have selected to **sync only assigned users and groups** from the provisioning settings. Select **Users and groups** from the navigation:



Select the + Add user/group button to assign access to the SCIM application on a user or group level. The following sections describe how modifying users and groups in Azure will impact their counterparts in Bitwarden:

Users

If **Provision Microsoft Entra ID Users** has been enabled in your Mappings, the following actions are taken:

- When a new user is assigned in Azure, the user is invited to your Bitwarden organization.
- When a user who is already a member of your organization is assigned in Azure, the Bitwarden user is linked to the Azure user through their UserName value.
 - Users linked in this way are still subject to the other workflows in this list, however values like displayName and externalId/ma ilNickname are not automatically changed in Bitwarden.
- When an assigned user is disabled via the accountEnabled property in Azure, the user has their access to the organization revoked.
- When an assigned user is "soft" deleted in Azure, the user has their access to the organization revoked.
 - When the user is permanently deleted in Azure, the user is removed from the organization.
- When an assigned user is removed from the Enterprise application in Azure, the user has their access to the organization revoked.
- When an assigned user is removed from a group in Azure, the user is removed from that group in Bitwarden but remains a member of the organization.

Groups

If you have Provision Microsoft Entra ID Groups enabled in your Mappings, the following actions are taken:

• When a new group is assigned in Azure, the group is created in Bitwarden.

- Group members who are already members of your Bitwarden organization are added to the group.
- Group members who are not already members of your Bitwarden organization are invited to join.
- When a group that already exists in your Bitwarden organization is assigned in Azure, the Bitwarden group is linked to Azure through the displayName and externalId/objectId values.
 - Groups linked in this way will have their members synced from Azure.
- When a group is renamed in Azure, it will be updated in Bitwarden as long as the initial sync has been made.
 - When a group is renamed in Bitwarden, it will be changed back to what it's named in Azure. Always change group names Azureside.

Start provisioning

Once the application is fully configured, start provisioning by selecting the > Start provisioning button on the enterprise application's Provisioning page:

	_ Ktart provisioning Stop prov	/isioning C Restart provisioning 🖉 Edit provisioning 🖓 Provision on demand \mid 💍 Refresh 🛛 🕂 Got feedback?
() Overview		
$\mathcal{P}_{\!\!\mathcal{B}}$ Provision on demand	Current cycle status	Statistics to date
Manage	Initial cycle not run.	
Provisioning		 View provisioning details 0% complete
Users and groups		 View technical information
Expression builder	View provisioning logs	
Monitor		
Provisioning logs	Manage provisioning Update credentials	
Audit logs	Edit attribute mappings	
💡 Insights	Add scoping filters Provision on demand	
Troubleshoot		
New support request		

Start provisioning

Finish user onboarding

Now that your users have been provisioned, they will receive invitations to join the organization. Instruct your users to accept the invitation and, once they have, confirm them to the organization.

() Note

The Invite \rightarrow Accept \rightarrow Confirm workflow facilitates the decryption key handshake that allows users to securely access organization vault data.